



UDDI for OpenVMS, based on UDDI4 (Universal Description, Discovery, and Integration)

Installation Guide and Release Notes

UDDI for OpenVMS Version 1.0
Based on UDDI4J Version 2.0.2, licensed under the IBM Public License V1.0
HP-VMS-UDDI-V0100--1.PCSI

January 2005

Contents

Before Installing UDDI for OpenVMS

- Hardware Prerequisites
- Software Prerequisites

Downloading and Installing UDDI

- Downloading the Kit
- Installing the Kit
- Configuration Tips
- Removing the Kit

After Installing UDDI for OpenVMS

Release Notes

Support

Before Installing UDDI for OpenVMS

Hardware Prerequisites

UDDI for OpenVMS is available on OpenVMS Alpha and OpenVMS Industry Standard 64.

Disk Space Requirements

Downloading the UDDI Version 1.0 PCSI file requires approximately 6610 blocks (3.22 MB) of disk space. Installing the product requires an additional 6705 blocks (3.27 MB).

Software Prerequisites

The following software is required for UDDI.

Operating system:

- OpenVMS I64 Version 8.2 or higher
- OpenVMS Alpha Version 7.3-1 or higher

For both OpenVMS I64 and OpenVMS Alpha systems:

- HP Software Development Kit (SDK) *for the Java™ Platform* Version 1.3.1 (or higher)
- All patches required for the Java SDK. Check the SDK documentation for the version of Java you are installing to be sure that you have all prerequisite OpenVMS operating system patches.
- SOAP Toolkit Version 2.0 or higher for OpenVMS, available from <http://www.hp.com/products/openvms/soap/>
- JAXP-1.1 compliant XML parser such as Xerces or Crimson must be configured before the UDDI product will operate. (However, you can install UDDI without an XML parser being configured.)

Note: The Crimson parser is included with the Java SDK Version 1.4 (or higher). However, HP recommends using the Apache Xerces XML parser because of known bugs using UDDI4J and Crimson. (Specifically, some of the samples are known to not run correctly when using Crimson.) OpenVMS provides support for the Apache Xerces parser in the product: XML-J for OpenVMS Version 2.0 or higher for OpenVMS, available from <http://www.hp.com/products/openvms/xml/>

Downloading and Installing UDDI

Downloading the Kit

The UDDI software is available for the Alpha and I64 platforms.

The UDDI PCSI kit is included with the OpenVMS I64 and OpenVMS Alpha layered product distributions. A compressed, self-extracting file is also available for download from the UDDI web site at <http://www.hp.com/products/openvms/uddi/>. Use the DCL RUN command to expand the compressed file.

Installing the Kit

Before you begin installing UDDI for OpenVMS, be sure you have met the prerequisites for this product.

Note: The BYPASS, GRPNAM, and SYSNAM privileges are required to install UDDI.

To install the UDDI for OpenVMS kit, enter the following command:

```
$ PRODUCT INSTALL UDDI
```

For a description of the features you can request with the PRODUCT INSTALL command when starting an installation such as running the IVP, purging files, and configuring the installation, see the *POLYCENTER Software Installation Utility User's Guide*.

As the installation procedure progresses, the system displays information similar to the following:

```
$ PRODUCT INSTALL UDDI /SOURCE=DISK:[UDDI_KIT] /DEST=DISK:[UDDI]
```

```
The following product has been selected:
  HP VMS UDDI V1.0                      Layered Product
```

```
Do you want to continue? [YES]
```

```
Configuration phase starting ...
```

```
You will be asked to choose options, if any, for each selected product and for
any products that may be installed to satisfy software dependency requirements.
```

```
HP VMS UDDI V1.0: UDDI V1.0 for OpenVMS
```

```
(C) 2004 Hewlett-Packard Development Company, L.P.
```

```
* This product does not have any configuration options.
```

```
Execution phase starting ...
```

```
The following product will be installed to destination:
  HP VMS UDDI V1.0                      DISK:[UDDI.]
```

```
Portion done: 0%...20%...30%...40%...50%...60%...70%...80%...90%
```

```
*****
Defining system logical UDDI$ROOT...
```

```
Please add the logical UDDI$ROOT in SYS$MANAGER:SYLOGICALS.COM
```

```
For example: $define/system/trans=concealed/nolog UDDI$ROOT DISK:[UDDI.uddi4j.]
```

```
*****
...100%
```

```
The following product has been installed:
  HP VMS UDDI V1.0                      Layered Product
```

```
$
```

After Installing UDDI

After the installation is complete, perform the following tasks.

1. Run the validation tests. Enter the following command:

```
$ @uddi$root:[openvms]UDDI-IVP
```

The following output is displayed:

```
Starting UDDI IVP...
```


Portion done: 0%...10%...20%...30%...40%...50%...60%...70%...80%...90%...100%

The following product has been removed:

HP VMS UDDI V1.0

Layered Product

\$

Release Notes

This section contains notes on the current release of UDDI for OpenVMS.

There are currently no release notes for the Version 1.0 kit.

Support

Customer Release Version

Support for UDDI for OpenVMS is provided under existing OpenVMS service agreements through standard support channels. See HP support at http://welcome.hp.com/country/us/en/contact_us.html for worldwide support center telephone numbers.

If you do not have a support contract and are not interested in acquiring one, you can informally exchange information with other users in the OpenVMS newsgroup `comp.os.vms`.

For technical feedback to the UDDI for OpenVMS engineering team, please send mail to OpenVMSUDDI@hp.com.
